3.1 Get methods

```
string fifo_hid.get_reset_name();
string fifo_hid.get_clock_name();
string fifo_hid.get_rd_clock_name();
string fifo_hid.get_wr_clock_name();
string fifo_hid.get_push_name();
string fifo_hid.get_pop_name();
string fifo_hid.get_full_name();
string fifo_hid.get_empty_name();
string fifo_hid.get_wr_data_name();
string fifo_hid.get_rd_data_name();
string fifo_hid.get_valid_name();
```

3.2 Csl_fifo get methods

```
string fifo_hid.get_reset_name();
DESCRIPTION:
```

It gets the name for the reset port of fifo.

[Get methods]

Sets the reset name for a unit named *u* using get reset name() method.

```
CSL CODE
    csl_fifo FO{
    FO() {
    set_width(32);
    set_depth(4);
    set_reset_name("rst");
    }
    ;;
    csl_unit u{
    csl_signal sig;
    FO FO;
    u() {
```

set signal prefix(FO.get reset name());}

VERILOG CODE

};

```
string fifo_hid.get_clock_name();
DESCRIPTION:
```

It get the name for the clock port of fifo.

[Get methods]

Sets the clock name for a unit named *u* using get clock name() method.

```
CSL CODE
```

```
csl_fifo FO{
FO() {
    set_width(32);
    set_depth(4);
    set_clock_name("clk");
};
csl_unit u{
    csl_signal sig;
FO FO;
    u() {
    set_signal_prefix(FO.get_clock_name());
    };
```

VERILOG CODE

```
string fifo_hid.get_rd_clock_name();
DESCRIPTION:
```

It gets the name for the read clock port of fifo.

[Get methods]

Sets the read clock name for a unit named *u* using get_rd_clock_name() method.

```
CSL CODE
```

```
csl_fifo FO{
FO(){
set_width(32);
set_depth(4);
set_rd_clock_name("rd_clk");
};
csl_unit u{
csl_signal sig;
FO FO;
u(){
set_signal_prefix(FO.get_rd_clock_name());
};
```

```
string fifo_hid.get_wr_clock_name();
DESCRIPTION:
```

It gets the name for the write clock port of fifo.

[Get methods]

Sets the write clock name for a unit named *u* using get wr clock name() method.

CSL CODE

```
csl_fifo FO{
FO() {
    set_width(32);
    set_depth(4);
    set_wr_clock_name("wr_clk");
    };
    csl_unit u{
    csl_signal sig;
    FO FO;
    u() {
    set_signal_prefix(FO.get_wr_clock_name()); }
};
```

VERILOG CODE

```
string fifo_hid.get_push_name();
DESCRIPTION:
```

It gets the name for the push port of fifo.

[Get methods]

Sets the push port name for a unit named *u* using get_push_name() method.

```
CSL CODE
    csl_fifo FO{
    FO() {
    set_width(32);
    set_depth(4);
    set_push_name("push");
    }
};
    csl_unit u{
    csl_signal sig;
    FO FO;
    u() {
```

set_signal_prefix(FO.get_push_name());}

VERILOG CODE

};

```
tring fifo_hid.get_pop_name();
DESCRIPTION:
```

It gets the name for the pop port of fifo.

[Get methods]

Sets the pop port name for a unit named *u* using get pop name() method.

CSL CODE

```
csl_fifo FO{
FO(){
set_width(32);
set_depth(4);
set_pop_name("pop");
}
};
csl_unit u{
csl_signal sig;
FO FO;
u(){
set_signal_prefix(FO.get_pop_name());
};
```

VERILOG CODE

```
string fifo_hid.get_full_name();
DESCRIPTION:
```

It gets the name for the full port of fifo.

[Get methods]

Sets the full port name for a unit named *u* using get_full_name() method.

```
CSL CODE
    csl_fifo FO{
    FO() {
    set_width(32);
    set_depth(4);
    set_full_name("full");
    };
    csl_unit u{
    csl_signal sig;
    FO FO;
    u() {
    set_signal_prefix(FO.get_full_name());
    };
}
```

```
string fifo_hid.get_empty_name();
DESCRIPTION:
```

It gets the *name* for the empty port of fifo.

[Get methods]

Sets the empty port name for a unit named *u* using get empty name() method.

CSL CODE

```
csl_fifo FO{
FO() {
    set_width(32);
    set_depth(4);
    set_empty_name("empty");
    };
    csl_unit u{
    csl_signal sig;
    FO FO;
    u() {
    set_signal_prefix(FO.get_empty_name()); }
};
```

VERILOG CODE

```
string fifo_hid.get_wr_data_name();
DESCRIPTION:
```

It gets the name for the wr data port of fifo.

[Get methods]

Sets the write data port name for a unit named *u* using get wr data name() method.

CSL CODE

```
csl_fifo FO{
FO() {
    set_width(32);
    set_depth(4);
    set_wr_data_name("write_data");
    };
    csl_unit u{
    csl_signal sig;
    FO FO;
    u() {
        set_signal_prefix(FO.get_wr_data_name());
    };
};
```

```
string fifo_hid.get_rd_data_name();
DESCRIPTION:
```

It gets the name for the rd data port of fifo.

[Get methods]

Sets the read data port name for a unit named *u* using get rd data name() method.

```
CSL CODE
```

```
csl_fifo FO{
FO() {
    set_width(32);
    set_depth(4);
    set_rd_data_name("read_data");
    };
    csl_unit u{
    csl_signal sig;
    FO FO;
    u() {
        set_signal_prefix(FO.get_rd_data_name());
    };
}
```

```
string fifo_hid.get_valid_name();
DESCRIPTION:
```

It gets the name for the valid port of fifo.

[Get methods]

Sets the valid port name for a unit named *u* using get valid name() method.

CSL CODE

```
csl_fifo FO{
FO() {
    set_width(32);
    set_depth(4);
    set_valid_name("valid");
};
csl_unit u{
    csl_signal sig;
FO FO;
    u() {
    set_signal_prefix(FO.get_valid_name());
    };
```